

Segment Installation Procedures
COE Web Help Software (COEWEBHelpSW)
Version 1.0.0.1 (HP-UX 10.20)

September 29, 1997

Table of Contents

Preface	ii
1. Installation Procedures	1
1.1 Scope	1
1.1.1 Identification	1
1.1.2 System Overview	1
2. Referenced Documents	3
3. System Environment	5
3.1 System Requirements	5
3.1.1 Hardware Requirements	5
3.1.2 Operating System Requirements	5
3.1.3 Kernel Requirements	5
3.2 System and Site Preparations	5
3.2.1 System Configuration	5
3.2.2 Operation System Preparation	5
3.2.3 Tape/Disk Preparation	5
4. Installation Instructions	7
4.1 Media Booting Procedures	7
4.2 Installation Procedures for the COEWEBHelpSW Segment	7
4.3 Installation of Upgrades	7
4.4 Installation Verification	7
4.5 Initializing the Software	8
4.6 List of Changes and Enhancements	8
4.7 Important Considerations	8
5. Notes	9

Preface

The following conventions are used in this document:

Bold	Used for information that is typed, pressed, or selected in executables and instructions. For example, select connect to host .
<i>Italics</i>	Used for file names, directories, scripts, commands, user IDs, document names, and Bibliography references; and any unusual computerese the first time it is used in text.
<u>Underline</u>	Used for emphasis.
Arrows <>	Used to identify keys on the keyboard. For example <Return>.
“Quotation Marks”	Used to identify informal, computer-generated queries and reports, or coined names; and to clarify a term when it appears for the first time. For example “Data-Generation Report.”
Courier Font	Used to denote anything as it appears on the screen or command lines. For example <code>tar xvf dev/rmt/3mm</code> .
Capitalization	Used to identify keys, screen icons, screen buttons, field, and menu names.

1. Installation Procedures

1.1 Scope

The Installation Procedures (IP) outlined in this document pertain to the Common Operating Environment (COE) Web Help Software (COEWEBHelpSW) segment, Version 1.0.0.1 (V1.0.0.1). This segment is delivered for the Defense Information System (DII) for both Hewlett-Packard (HP)-based and Solaris-based platforms.

1.1.1 Identification

This section contains identification information for the COEWEBHelpSW segment:

Segment Name:	COE Web Help Software
Segment Type:	SOFTWARE
Prefix:	WHSW
Home Directory:	/h/COEWEBHelpSW
Required License:	None
Version Number:	1.0.0.1
Platform:	HP (UNIX) Workstation/HP-UX 10.20

1.1.2 System Overview

This section contains system overview information for the COEWEBHelpSW segment:

Purpose:	The COEWEBHelpSW segment contains a sample software segment and application source and executable code which, along with the associated COE Web Help Data (COEWEBHelpDATA) segment, demonstrates how a developer can integrate Web-based help documents into a mission application's operating environment.
Usage:	Developers may use the COEWEBHelpSW segment as a development aid to develop and implement segment-based Web help documents.
References:	The <i>COE Web Help Developer's Guide</i> which was delivered with the associated COEWEBHelpDATA segment. Users may also refer to the on-line version of this manual by installing and running the sample application contained in this segment, and selecting the COE Web Help menu item on the Help menu.

This page intentionally left blank.

2. Referenced Documents

The following documents are referenced in this IP:

- C “Installation Procedures - COE Web Help Software Segment” delivered with the COEWEBHelpSW segment, V1.0.0.1.
- C “COE Web Help Developer’s Guide” delivered with the COEWEBHelpDATA segment, version 1.0.0.1

This page intentionally left blank.

3. System Environment

3.1 System Requirements

The following subsections describe the system requirements to install the COEWEBHelpSW segment.

3.1.1 Hardware Requirements

The following HP hardware is necessary to install the COEWEBHelpSW segment:

- C HP-UX 10.20
- C 55 KB of disk space
- C 16000 KB of memory

3.1.2 Operating System Requirements

The HP operating system must be at least HP-UX 10.20 to install the COEWEBHelpSW segment.

3.1.3 Kernel Requirements

The following DII COE Kernel is required to install the COEWEBHelpSW segment:

DII COE Kernel V3.2 for HP-UX 10.20 for the HP version of COEWEBHelpSW.

3.2 System and Site Preparations

3.2.1 System Configuration

None.

3.2.2 Operation System Preparation

None.

3.2.3 Tape/Disk Preparation

Rewind tape before beginning the installation process.

This page intentionally left blank.

4. Installation Instructions

4.1 Media Booting Procedures

None.

4.2 Installation Procedures for the COEWBHelpSW Segment

Use the following steps to install the COEWBHelpSW segment:

Step 1: Select **COE Web Help Software Segment** from the COE Installer's Select Software to Install window and press the **INSTALL** button.

Step 2: Respond appropriately to any COEInstaller prompts.

4.2.3 De-Installation Procedures

Use the following steps to de-install the COEWBHelpSW segment:

Step 1: Select **COE Web Help Software Segment** from the COE Installer's Currently Installed Segments window and press the **DEINSTALL SOFTWARE** button.

Step 2: Respond appropriately to any COEInstaller prompts.

4.3 Installation of Upgrades

None.

4.4 Installation Verification

To verify that this software has been installed, execute the following command:

```
/h/COEWBHelpSW/bin/WHWSW_COEWBSampleApp
```

When the COE Web Help Sample Application main window is displayed, select the **COE Web Help** menu item from the Help menu. The *COE Web Help Developer's Guide* should be displayed in the Netscape browser window that appears.

NOTE: The associated segment, COE Web Help Data (V1.0.0.1), should be de-installed before de-installing the COEWBHelpSW segment.

4.5 Initializing the Software

Not required.

4.6 List of Changes and Enhancements

Not applicable.

4.7 Important Considerations

None.

5. Notes

The associated segment, COE Web Help Data Segment (V1.0.0.1), should be de-installed before de-installing the COEWEBHelpSW segment.

This page intentionally left blank.